

# pEASY®-T1 Cloning Kit

Please read the user manual carefully before use.

Cat. No. CT101

#### Storage

*Trans*1-T1 Phage Resistant Chemically Competent Cell at -70°C for six months; others at -20°C for nine months Descriptions

pEASY ®-T1 Cloning Kit is designed for cloning and sequencing Taq-amplified PCR products.

- 5 minutes fast ligation of *Taq*-amplified PCR products.
- Kanamycin and Ampicillin resistance genes for selection.
- Easy blue/white selection.
- T7 promoter, M13 forward and M13 reverse primers for sequencing.
- T7 promoter for *in vitro* transcription.
- *Trans* 1-T1 Phage Pesistant Chemically Competent Cells, high transformation efficiency (>10<sup>9</sup> cfu/μg pUC19 DNA) and fast growing.

### Kit Contents

Commonant	CT101-01	CT101-02
Component	(20 rxns)	(60 rxns)
pEASY ®-T1 Cloning Vector (10 ng/μl)	20 μ1	3×20 μl
Control Template (5 ng/µl)	5 μl	5 µl
Control Primers (10 µM)	5 μ1	5 μ1
M13 Forward Primer (10 μM)	50 µl	150 µl
M13 Reverse Primer (10 μM)	50 μl	150 µl
Trans1-T1 Phage Resistant Chemically Competent Cells	10×100 μl	30×100 μl

# Preparation of PCR Products

- 1. Primer requirement: primer cannot be phosphorylated
- 2. PCR Enzyme: Taq DNA polymerases
- 3. Reaction conditions: in order to ensure the integrity of amplification products, 5-10 minutes of post-extension step is required. After amplification reaction, use agarose gel electrophoresis to verify the quality and quantity of PCR product

### Setting Up the Cloning Reaction System

Add following components into a microcentrifuge tube.

PCR products 0.5-4 µl (can be increased or reduced based on PCR product yield, no more than 4 µl)

*pEASY* ®- T1 Cloning Vector 1 μ

Gently mix well, incubate at room temperature (20°C-37°C) for 5 minutes. After reaction, place the tube on ice.

1. Optimal amount of insert

Molar ratio of vector to insert = 1:7 (1 kb, ~20 ng; 2 kb, ~40 ng)

- 2. Optimal volume of vector: 1 μl
- 3. Optimal reaction volume: 3~5 μl
- 4. Optimal incubation time
- (1) 0.1~1 kb (including 1 kb): 5~10 minutes
- (2)  $1\sim2$  kb (including 2 kb):  $10\sim15$  minutes
- (3)  $2\sim3$  kb (including 3 kb):  $15\sim20$  minutes
- (4) ≥3 kb: 20~30 minutes

Use the maximum incubation time if the insert is gel purified.





5. Optimal incubation temperature: for most PCR inserts, the optimal temperature is about 25°C; for some PCR inserts, optimal results can be achieved with higher temperature (up to 37°C).

#### Transformation

- 1. Add the ligated products to 50 μl of *Trans*1-T1 Phage Resistant Chemically Competent Cell and mix gently (do not mix by pipetting up and down).
- 2. Incubate on ice for 20~30 minutes.
- 3. Heat-shock the cells at 42°C for 30 seconds.
- 4. Immediately place the tube on ice for 2 minutes.
- 5. Add 250 µl of room temperature SOC or LB medium. Shake the tube at 37°C (200 rpm) for 1 hour.
- 6. In the meantime, mix 8 μl of 500 mM IPTG with 40 μl of 20 mg/ml X-gal. Spread them evenly onto a selective LB plate. Place the plate at 37°C for 30 minutes.
- 7. Spread 200 μl or all transformants on the pre-warmed plate. Incubate at 37°C overnight.

# Identification of Positive Clones and Sequencing

### Analysis of positive clones

- 1. Transfer 5~10 white or light blue colonies into 10 μl Nuclease-free Water and vortex.
- 2. Use 1 µl of the mixture as template for 25 µl PCR using M13 forward and M13 reverse primers.
- 3. PCR reaction conditions

94°C	10 min	
94°C	30 sec —	_
55°C	30 sec	30 cycles
72°C	x min*—	)
72°C	5.10 min	

- \* (depends on the insert size and PCR enzymes) the PCR product size from vector self-ligation is 199 bp.
- 4. Analyze positive clones by restriction enzyme digestion and DNA sequencing.

  Inoculate positive clones on LB/Amp<sup>+</sup> or LB/Kan<sup>+</sup> liquid medium, grow at 37°C for 6 hours at 200 rpm. Isolate plasmid DNA by plasmid MiniPrep Kit. Analyze colonies by restriction enzyme digestion with proper restriction endonuclease.

#### Sequencing

Analyze the sequence by sequencing with M13 F, M13 R and T7 promoter.

#### PCR for control insert (700 bp)

Component	Volume	Final Concentration
Control Template (5 ng/µl)	1 μ1	0.1 ng/μl
Control Primers (10 µM)	1 μ1	0.2 μΜ
2×EasyTaq® PCR SuperMix	25 μ1	1×
Nuclease-free Water	Variable	-
Total volume	50 μl	-


# Thermal cycling conditions for control insert

94°C	2-5 min	
94°C	30 sec	
55°C	30 sec	30 cycles
72°C	1 min	
72°C	10 min	

Ligate 1 µl of control PCR insert with 1 µl vector. Hundreds of colonies should be produced with cloning efficiency over 90%.








LacZα fragment: bases 1-544
M13 reverse priming site: bases 205-221
Multiple cloning site: bases 234-354
T7 promoter priming site: bases 361-380
M13 forward priming site: bases 387-403
f1 origin: bases 545-982

Kanamycin resistance ORF: bases 1,316-2,110 Ampicillin resistance ORF: bases 2,128-2,988

pUC origin: bases 3,133-3,806



For research use only, not for clinical diagnosis. Service telephone +86-10-57815020 Service email complaints@transgen.com

